

iGo8 sys.txt Alle verdier

Bidrag fra Administrator
 Tuesday 24. July 2012
 Sist oppdatert Wednesday 25. July 2012

Oversikt over instillinger i sys.txt /system.ini.

```

;### Possible sections igo8 PDA/PNA, read by iGO in order:

;###

;### 0) Defaults hardcoded into IGO8.EXE

;### 1) DATA.ZIPui_igo8commonSKINCFG.INI

;### 2) DATA.ZIPui_igo8320_240SKINCFG.INI (or other resolution)

;### 3) DATA.ZIPproject_configIGO8_GENERIC.INI

;### 4) igo8savesystem.ini (your settings are stored here)

;### 5) this: sys.txt

;### *) CONFIGDEVICESyourdevice.INI

;###

;### tweakradje 11 feb 2010 (iGo8 R3)

; *** PLEASE KEEP ABC ORDER FOR CONFIG GROUPS! ***

;### NOTE:leave default value only if you are sure that it is not set

;### in any of the files above

;#####

;[registry]

;oninit1="HKLMSystemCurrentControlSetControlPowerTimeoutsACSSuspendTimeoutWORD:0"

;onexitreset1="HKLMSystemCurrentControlSetControlPowerTimeoutsACSSuspendTimeoutWORD"

;onexit1=""

;HKCU HKLM HKCR HKU

;DWORD STR BYTE

[2d]

screen_pixel_per_dem_pixel=100 ;(100)

carcenter_x=-1 ;(-1)

carcenter_y=30 ;(-1) 0=top of arrow

```

```
mincarsize=100      ;()
mincarsize_zoomlevel=5000
maxcarsize=180      ;()
maxcarsize_zoomlevel=200

draw_polygon_contours=0      ;(1) more speedy
render_during_animation=1    ;(0)
;full_render_delay_after_drag=200 ;(150)
;double_pixel_enabled=0      ;(0)
;double_pixel=0              ;(0)
;pretty_render_antialias=0    ;(0)
;pretty_render_hires=0        ;(0)

show_guidance_strip=1        ;(1) colors guidancestrip and guidancestrip_ext
;guidancestrip_stretch_forward=1
;guidancestrip_stretch=25    ;(25)
;guidancestrip_length=4      ;
guidancestrip_thickness=0.4  ;(0.4) strip width
guidancestrip_width=0.8      ;(0.5) arrow head width
;###extra for 2d
;guidancestrip_outline_thickness=2 ;(2)

show_guidance_arrows=0      ;(1)
guidancearrow_disappearlevel=600
guidancearrow_maxshift=20   ; shift arrow for better vis.
minguidancearrowsize=20
maxguidancearrowsize=65
minguidancearrowsize_zoomlevel=1200
maxguidancearrowsize_zoomlevel=0

;show_planned_route_arrows=1 ;(1)

;#####
```

```
ambient=x00900190 ;(0x00000190)

globe_ambient=x000003D4 ;(0x3d4 blueish)

distance_terrain_resolution=1 ;(0)

:disable_car_normals=1 ;(0)

show_guidance_strip=1 ;(1) colors guidancestrip and guidancestrip_ext

;guidancestrip_stretch_forward=1

;guidancestrip_stretch=25 ;(25)

;guidancestrip_length=4 ;

guidancestrip_thickness=0.1 ;(0.1) strip width

guidancestrip_width=0.8 ;(0.5) arrow head width

;### extra for 3d

elevate_guidance_strip=1 ;(1) elevate above road

;guidancestrip_elevation=0.7 ;(0) height above manœuvre

guidancestrip_elevation=0.1

show_guidance_arrows=0 ;(1) colors in day[night]2d[3d]color.ini

show_planned_route_arrows=1 ;(1) colors in day[night]2d[3d]color.ini

;### fading buildings

fade_around_cursor=1 ;(0) ??

fade_use_overlap=1 ;(0)

fade_overlap_tolerance=20 ;(50)

fade_distance_for_car=200 ;(20)

fade_distance_for_guidance_arrow=50 ;(50)

show_tracklogs=0 ;(0)

;jun08 version

;car_day=car.mdl ; 3d car and colors in day[night]2d[3d]color.ini

;car_day=sports_car.mdl

;car_night=sports_car.mdl

;ghost_day=sports_car.mdl

;ghost_night=sports_car.mdl

;car_day=car_blaupunkt.mdl
```

```
;car_night=car_blaupunkt.mdl
;ghost_day=car_blaupunkt.mdl
;ghost_night=car_blaupunkt.mdl
;car_day=becker_car_gps.mdl
;car_night=becker_car_gps.mdl
;car_day=car_spaceship.mdl
;car_day=Porsche.bmp ; bmp no worky (
;car_night=car_night.mdl
;ghost_day=car_ghost.mdl
;ghost_night=car_ghost.mdl
;ghost_day=becker_car_ghost.mdl
;ghost_night=becker_car_ghost.mdl

road_clip_plane_to_camera_height=1 ;(1)
road_clip_plane_camera_delta=10 ;(10)

guidancearrow_first_size=1.5 ;(?) scale of 1st arrow
guidancearrow_first_alpha=20 ;(20) transp of 1st arrow
guidancearrow_second_size=1.0 ;(?)
guidancearrow_second_alpha=10 ;(10)
;guidancearrow_width=1.0 ;
;guidancearrow_thickness=0.1 ;
;guidancearrow_skew=0.5 ;
;guidancearrow_zoomfactor=0.07 ;(?)
;guidancearrow_contour=2 ;(1)

use_all_building_textures=0 ;(1) less memory

;track_screen_ratio=
;min_track_screen_ratio=

;min_track_distance=
;max_track_distance_lower=
;max_track_distance_upper=

;min_track_segments_shown_1=
```

```
;max_track_segments_shown_1=
```

```
;min_poly_distance=
```

```
;max_poly_distance_lower=
```

```
;max_poly_distance_upper=
```

```
min_poly_segments_shown_1=200 ;makes map drawing a lot faster
```

```
max_poly_segments_shown_1=400 ;makes map drawing a lot faster
```

```
##### 3d landmark and buildings render distances, see also $commonclip_planes.ini
```

```
building_camera_distance_near=100 ;(100)
```

```
building_camera_distance_medium=200 ;(120)
```

```
building_camera_distance_far=400 ;(150)
```

```
#####
```

```
[3d_config]
```

```
;frame_fontsize_muler=1.3 ;(1.0) label font factor, CONFIGDEVICES INI file
```

```
roadsign_lines_per_screen=14 ;(30) max streetnames on the screen, affects fontsize in 3D
```

```
disable_roadsign_navigation_mode=0 ;(1) nice text balloons roadnames in nav mode
```

```
rotated_roadsigns=1 ;(0) roadnames will align with the roads themselves
```

```
;default_label_colors=0 ;(0)
```

```
;left_transparent_border=10 ;(0)
```

```
;right_transparent_border=10 ;(0)
```

```
;top_transparent_border=25 ;(0)
```

```
;bottom_transparent_border=35 ;(0)
```

```
[config]
```

```
R2L=0
```

```
autoset2donmap=1 ;(0)
```

```
autoset3doncockpit=1 ;(0)
```

```
HideRoadAltName=0 ;(1)
```

```
OverspeedRewarnBelow=1 ;(1)
```

```
OverspeedDelayBetweenWarning=120 ;()
```

```
;voicerarity=70 ;(100)
```

```
nmaxstrapdistance=22 ;(30) radius for snap gps pos to the road, also[ strapon]
```

```
;SafeModeMinSpeed=40 ;(???)
```

```
;strapOnlyOverspeed=0 ;(-1)
```

```
#####
```

```
[bluetooth]
```

```
;send_showphoneui_on_dial=1 ;(0)
```

```
#####
```

```
[debug]
```

```
logitiner=full ;off
```

```
;gui_x=320
```

```
;gui_y=240
```

```
;disable_roundabout_dir=1 ;(0) no rndbt directions
```

```
skip_platformlock=1 ;(0) hmmm...
```

```
;restart_mode_in_file=1 ; ezrider R3
```

```
route_dragmode=1 ;GetSysEntry Amigo
```

```
ads=1 ;GetSysEntry Amigo
```

```
### variables that are queried from UI files
```

```
### in setting.ini >> GETSYSENTRY "screen_calibration" "debug" 0 vScreenCalibration
```

```
screen_calibration=1 ;(?) force screen calib option
```

```
;monkey_restriction=no
```

```
getupdates=0
```

```
minimize_button=1
```

```
adaptive_2d=1 ;(0)
```

```
bringtotop_afterresume=1 ;(1)
```

```
;routeplan_mode=test ;(test)
```

```
;routeplan="a route plan file"
```

```
### this creates detailed running logfile for tts etc
```

```
;log_1="Storage Cardigo8igo8_debug.log::5"
```

```
;already_running_assert=0 ;(1) ???  
  
;show="Petrol_Station,Parking" ;something with pois ????  
  
;demscheduler_sanity_checks=1 ;(0)  
;disable_northlock=1 ;(0)  
  
;allow_discard_sound_queue=1 ;(1)  
;terrain_test=1 ;(0)  
;road_test=1 ;(0)  
;shape_test=1 ;(0)  
;test_map_name="All" ;All  
;Full2d_test=1 ;(0)  
;Full3d_test=1 ;(0)  
  
raster_quality=1 ;(2)  
tunnel_mode=1 ;(1) switch to night in tunnel and announce tunnel  
ambient=400 ;(400) ambient light?  
raster_google_maps=0 ;(0) need contentraster folder  
  
;monkeytest_scriptfile="autotest/autotest.txt"  
;monkeytest_logfile="autotest/logfile.txt"  
;monkeytest_command_delay="1000"  
;monkeytest_recordfile="autotest/recorded.txt"  
  
BuildNewOrderList=1 ;(0)  
;leak_check=1 ;(1)  
;save_screen_debugclick=0 ;(0)  
;save_crash_bmp=1 ;(0) saves crash.bmp  
;ignore_pause=0 ;(0)  
phone_available=1 ;(0)  
bluetooth_available=1 ;(0)  
;force_daylight=1 ;(0)  
;catch_all_keys=1 ;(1)  
;disable_3d_labels=0 ;(0) no text labels (streetname etc)
```

```
;tmc_weight=40 ;(100)

;long_click_time=300 ;(500)
one_line_msg_text=1 ;(1)

allowexit=1 ;(1)
;hide_win_taskbar=1 ;(1) like it says
render_without_focus=1 ;(0) renders even if igo8 window not in front
;memory_low_bound=0 ;(0) bits? kb?
;memory_check_interval=20000 ;(10000 msecs)

;max_memory=42000000 ;(0) something fro device ini
reserve_memory=2097152 ;(0) default 4Mb, don't use less that 1Mb (1mb=1048576 2mb=2097152 3mb=3145728)

;distterrain_max_transform_and_draw_farroads_time= 12 ;(12)
;distterrain_max_gen_farroadcell_num=4 ;(4)
;distterrain_max_gen_farroads_time=14 ;(14)
;distterrain_max_gen_supercell_time=16 ;(22) secs?
;distterrain_max_gen_supercell_num=6 ;(6)

;savesequence=1 ;(0) alotta screenshots
;screenshotfilename="\ffscreen_%05d.bmp" ;the def filename
;run_on_mio_mantas=1 ;(0)
topmost=0 ;(0)
nortc=0 ;(0) ???

;### moved fov to DEVICE INI 40 for 320x240, 50 for 480x272
;fov=45 ;(45) field of view (wider angle=slower, 3d car smaller)

; TTS settings
tts_min_ready_wav=1 ;(0)
tts_getaway_time=400 ;(0)
tts_expected_engine_delay=1200 ;(0)
;tts_log=1 ;(0)
;### end TTS

;supress_straight=0 ;(0)
```


;supress_highway_enter=0 ;(0)
;supress_leave_ferry=0 ;(0)
min_then_dist=20 ;(0) don't use 2nd call if less than...
;exit_after=1 ;(0) name exit numer last
auto_ignore=1 ;(0) tts intelligence?
;enable_roadshadow=1 ;(1)
;enable_roadsign=1 ;(1)
;enable_buildings=1 ;(1)
enable_landmark_occlusion=1 ;(1)
;log_power=0 ;(0)
;override_speed=0 ;(0)
;mute_os_key=0 ;(0)
;log_tmc=0 ;(0)
;no_tmc=0 ;(0)
;replay_tmc=1 ;(0)
tmc_all_stations=1 ;(0)
;hide_itiner_crossing=0 ;(0)
;log_network=0 ;(0)
no_depth_shading=0 ;(0)
no_extrapolation=0 ;(0)
use_conn_mgr=1 ;(1)
;log_phoneapi=0 ;(0)
gnome_dem_files=0 ;(0) searches for content/dem/gnome/52_2.dem etc
immediate_relief3d_dem=1 ;(1)
immediate_distterrain_dem=1 ;(0)
pin_sets_start=1 ;(0)
;compass_type=0 ;(0) only 1 compass.vpr
;disable_3d=0 ;(0) disables 3d buildings and roads
;double_pixel_mode=0 ;(0) 3d mode fastdraw
;doublepixel_stable_frame_time=1000 ;(1000) time in ms before leavin fastdraw
skip_eula=1 ;(0)
skip_lang_init=1 ;(0)

;loop_sim=1 ;(0)
smart_2d=1 ;(0)
earth=1 ;(0)

show_truck_info=1 ;(0)
;show_screensize=0 ;(0)
;show_arrows_on_route=1 ;(1) little arrows in direction of route
show_plural=1 ;(0) color road on slippery places
;show_residentonly=0 ;(0)
show_multinode_maneuvers=1 ;(0)
show_prohibited_maneuvers=0 ;(0)
show_priority_maneuvers=1 ;(0)
show_turn_penalty=1 ;(0)
show_lane_info=1 ;(0)
show_gps_pos=1 ;(0) little blue dot
show_signpost=1 ;(0)
show_original_signpost=1 ;(0)
show_pedestrian=1 ;(0)
;show_segmentdir=0 ;(0)
;show_segmentid=0 ;(0)
;show_oneway_3d=1 ;(1) 3d arrows in one way streets
show_oneway=1 ;(0) show one way on or off
;show_urn=0 ;(0)
;show_mapid=0 ;(0)
show_tmc=1 ;(0)
;show_performance=1 ;(0) cpu / mem / whatever bars on top of screen
;show_device_type=1 ;(0) handy for finding proper CONFIG<device.ini>
show_rawdisplay_info=0 ;(0) handy for seeing what igo chooses as display driver
show_prec_poi_detour=1 ;(0)
;show_lights=0 ;(0)
;show_ltn=1 ;(0)
show_roadid=1 ;(0)
show_historical_speed=1 ;(0)

show_speed_limit=1 ;(0)

;builtinborder=1 ;(1)

;mapstat=0 ;(0)

autosave=10000 ;(60000) save state every minute

;turn_penalty_multiplier=100 ;(100)

disable_outlookpoi=1 ;(0)

#####

[defaults]

doesn't work anymore

mainroadness=80 ;(100)

shortness=50 ;(20)

simplificationness=100 ;(100)

#####

[device]

;type="PIONEER749UC"

;type="PACKARD BELL GPS" ; see configdevices*.ini

;uselightapi=1

;usecompassapi=1

;reset_on_sd_remove=1 ;(0)

#####

[dynamiccompressor]

compressor="1"

;a0="56806"

;thrs="24703"

;ratio="8"

;gain="8"

#####

[feature]

tunnel_guidance=1 ;(0)

itiner_cityentry=1 ;(1)

text_guidance=0 ;(0)

signpost_coloring=1 ;(0)

tmc_event_coloring=1 ;(0) see day/night/2d/3dcolor.ini etc for tmc_event_color0..4

tmc_traffic_side=1 ;(0)

tmc_show_direction_arrows=1 ;(0)

#####

:[fleet_mgmt]

;api_ui_name="External Application"

#####

[folders]

;models="GFX" ;(is GFX folder files like car.mdl, arrow.mdl etc)

;secondary_root="igo8"

;models="contentcarLimousine_Silver"

;models="contentcarBuggy"

;models="contentcarSports_Car"

;models="contentcarStation_Wagon"

;models="contentcarTruck"

app="%SDCARD%/iGO8" ; change this if applicable

;sdcardpath="Storage Card"

;user_backup_path=""

;tracklog_folder="TRACKS"

;secondary_root="ROOT2"

;secondary_app="Storage Card/usericon,USB Disk/usericon"

;usb_trackexport_path="USB Disk"

;storage_trackexport_path="Storage Card"

;content="CONTENT"

```
;data="Storage CardiGo8Amigo" ;save folder
```

```
data="Storage CardiGo8"
```

```
;demo="DEFAULTSdemo" ; route???.dat
```

```
;lang="custom"
```

```
;voice="custom"
```

```
;textures="custom"
```

```
;buildings="custom"
```

```
;dem="custom"
```

```
;exe=""
```

```
;fonts="\windows\"
```

```
;osdir=
```

```
;usb_kmlpoi="USB Disk/poi"
```

```
kmlpoi="userdatapoi" ;"contentuserdatapoi"
```

```
kmlroute="userdataroute" ;"contentuserdataroute"
```

```
tts_nuance="Storage CardiGO8ScanSoftRealSpeakSolo" ;(ResidentFlashScanSoftRealSpeakSolo) ezrider3
```

```
;tts_nuance="Storage CardMioMapTTS_PPC"
```

```
tts_loq="Storage CardIGO8TTS_LOQ" ;becker
```

```
;mappath="Storage Cardigo8contentmap"
```

```
#####
```

```
[gestures]
```

```
;border_height=40 ;(40)
```

```
;border_width=34 ;(34?)
```

```
;movement_distance=100 ;(100)
```

```
;dir_change_distance=
```

```
#####
```

```
[gps]
```

```
background_navigation=1 ;(1) when minimized
```

logging=0 ; see also mydata.tracks

disable_advanced=0

;default_latitude=48.857004

;default_longitude=2.294760

;log_valid_time=0 ;(0)

;log_base_dir="/" ;("/")

;log_on_flash=0 ;(1)

read_total_timeout=50 ;(100)

read_buffer_size=128 ;(256)

Best set in CONFIGDEVICES INI file

;port=2

;port=1

;baud=4800

;protocol="auto" ;("auto") nmea sirf hippo

;devicename_template="COM%d:" ; so port=1 becomes COM1:

;send_init=0 ;(0)

;use_trickle_power=1 ;(0) only Sirf?

;maximise_baud=0 ;(0)

;set_messages=1 ;(1)

#####

something for device ini !!!

[gx]

;bpp=16

;width=320

;height=240

;x_pitch=2

;y_pitch=640

;fullscreen=

;buffer=

;buffer_offset=

;gx_disable_detect=

```
;pixel format is GDIDIRECT_FORMAT_565
```

```
;pixel_format=1
```

```
;gx_allow_gaps=
```

```
#####
```

```
[hack]
```

```
;junction_streets_in_phone_number=1
```

```
#####
```

```
[interface]
```

```
save_checksum=0
```

```
small_build=1 ;GetSysEntry Amigo
```

```
smart_history=1 ;GetSysEntry Amigo
```

```
show_musicplayer=0 ;GetSysEntry Amigo
```

```
show_pictureviewer=1 ;GetSysEntry Amigo
```

```
always_show_trafficsettings=1 ;GetSysEntry Amigo
```

```
; This threshold determines the roadname length above which
```

```
; no roadshield is shown in TMC list but roadname is merged into Location Info
```

```
; set -1 to always show roadshield, set 0 to always show merged string
```

```
tmc_roadname_length_threshold=-1
```

```
unreachable_viapoint_as_target=1
```

```
html_p_compliance=1
```

```
doublekey_manage=1 ;(0)
```

```
allow_all_hwkeys=1 ;(0)
```

```
;hide_mouse=1 ;(1)
```

```
;external_mp3_player_window_name=""
```

```
### read from UI file with GetSysEntry
```

```
;start_state="st_Start" ;or st_navigate???
```

```
;start_state=st_EasyMainMenu ;GetSysEntry Amigo
```

```
autoscroll_interval=100 ;(50)

;;;uifile="ui"

;check_bt_pairing=1 ;(0)
;bt_pairing_window="Enter Passcode"

useminaspect=0 ;(1)
distance_format=0 ;(0) meters
distance_limit_meters_1=500 ;(500)
distance_limit_meters_2=1000 ;(1000)
distance_limit_meters_3=10000 ;(10000)
;distance_limit_feet_1=100
;distance_limit_feet_2=1000
;distance_limit_feet_3=5120
;distance_limit_feet_4=
;distance_limit_feet_5=

poi_show_all_btn=1 ;(0) show phone button in poi screen
;restart_after_resume=1 ;(0)
;tmc_events_icon_set="smalltmc.spr" ;("smalltmc.spr")

inputtext_cursor_char1=0 ;??
inputtext_cursor_char2=0 ;??
emptylist_counter="1/1" ;("0/0")
emptylist_page_count=1 ;(0)
emptylist_page_number=1 ;(0)

;no_sec_in_time_span=0 ;(0)
;use_autohint=1 ;(1) for what?
;default_day_color=""
;default_night_color=""

compass_velocity=8 ;(10)

handle_autocamera_at_setgpsmode=1 ;(1)
;always_use_prec_disttype=1 ;(0)
;use_lower_round_at_prec_disttype=0 ;(0)
```


shutdown_time=0 ;(10) no shutdown timer!
round_mode=1 ;(0) dunno
;smartkey_for_multistrings=1 ;(1)
;order_max_length=300 ;(300)
laneinfo_signpost_enabled=1 ;(1)

use_mixed_country_state_list=1 ;(0)
;force_county_town_form=1 ;(0)
;force_na_county_town_form=1 ;(0)

city_hist_maxentriesnum=40 ;(18)

show_detailed_posinfo=2 ;(0) like postal code

one_line_msg_text=0 ;(1)

;restore_state_after_flyover=1 ;(1)
;use_separated_daynight_list=1 ;(0)
;theme=""
;newalignment=0 ;(0) align streetnames?
bilang_city=1 ;(0) show cityname in your and orig language
Recalc_voice=1 ;(1)
max_distance_for_route_to_poi=6000 ;(10.000)
;use_separated_safety_mode=1 ;(0) makes it slow
;use_separated_safety_in_mainview=1 ;(0) makes it slow
;theme="skinigo8_plus.zip"

skin=ui_igo8
;skin=ui_igo8_da
;skin=ui_igo_easy
;skin=ui_magellan
;skin=ui_becker
;skin=ui_blaupunkt
;skin=ui_mio_v5
;skin=ui_pioneer

```
;skin=ui_hp_sagan
```

```
;skin=ui_alpine
```

```
;skin=ui_limo
```

```
;resolution_dir=240_320
```

```
;resolution_dir=320_240
```

```
;resolution_dir=480_272
```

```
;resolution_dir=800_480
```

```
### settings for CONFIGDEVICES INI file
```

```
;width=320
```

```
;height=240
```

```
;wide=1
```

```
;vga=0
```

```
roffset=8 ;(8)
```

```
minzoomglobe=100000 ;() 100km 2d zoom before switching to globe view
```

```
minzoom2d=100 ;(100) tested!
```

```
;maxzoom2d=60000 ;(0)
```

```
defaultzoom2d=10000 ;(20000)
```

```
defaultzoom3d=50 ;(100) bigger than [map]3d_min_zoomlevel
```

```
;defaulttilt3d=7500 ;(6000) same as [map]3d_default_tiltlevel
```

```
initial_zoom_level=5000 ;(40000)
```

```
autotilt=0 ;(0) 1 2 makes the camera go up and down
```

```
;autotilt_minzoom3d=20 ;(20)
```

```
;autotilt_maxzoom3d=400 ;(400)
```

```
show_orientation=1 ;(0)
```

```
show_calibration=1 ;(0)
```

```
show_gps_config=1
```

```
show_tmc_config=1
```

```
show_exit=1
```

```
show_minimize=1
```

show_zoombar=1 ;(0) also see zoomscale_disappearing

show_kml_type=1 ;(1)

disable_3dstick_labels=1 ;(0)

mapfontscale=140 ; for 2d map (area,road,label?)

default_poi_icon="Contacts" ; see iconspoicontacts.icon

;mio=1 ;(1)

;screen_snap_distance=10 ;(20) snaps to start end etc on map click

;exit_on_restart=1 ;(0)

drive_carefully=0 ;(1)

use_spec_fav=1 ;(0) Home and Work?

spec_fav_count=2 ;(2) Home and Work?

#####

[itiner]

pass_via_distance=1 ;(0)

pass_destination_distance=1 ;(0)

pass_stop_speed=1 ;(0)

show_only_till_next_viapoint=0 ;(0)

show_prev_manuevers=1 ;(0)

show_only_ahead_of_car=1 ;(0)

#####

[keyboard]

panel_alpha="US English (QWERTY)"

panel_custom="Numbers"

;panels="config/keyboard.ini"

disable_lang_panels=0 ;(0) to select layout

;smart_housenumbers=1 ;(1)

```
;#####
```

```
[kml]
```

```
;default_icon=1
```

```
;#####
```

```
;#####
```

```
[loading]
```

```
;### read from UI file with GetSysEntry
```

```
usermode=0
```

```
;repaint_fg_wnd=1
```

```
;releaselangvoice=1 ;(0) ezrider R3
```

```
;reset_after_startfailure=0 ;(0)
```

```
;background_startup=1 ;(0) like it says
```

```
;background_startup_on_restart=0 ;(0)
```

```
;dont_force_focus=0 ;(0)
```

```
;dont_force_focus_on_restart=0 ;(0)
```

```
;
```

```
; see [loading] in ui_igo832_240skincfg.ini or project_configigo8_generic.ini
```

```
;
```

```
show_statustext=1
```

```
show_progressbar=0
```

```
progressbar_x=85
```

```
progressbar_y=134
```

```
;loading_bmp="loading.jpg"
```

```
;text_fontcolor=xFFFFFFF
```

```
;text_fontsize=30
```

```
;text_x=100
```

```
;text_y=400
```

```
;text_w=600
```

```
;text_align: LEFT = 0,CENTER = 1,RIGHT = 2 JUSTIFY = 3
```

text_align=1

;### test1

;show_phases=1

;phases_x=10

;phases_y=10

;phases_bmp="big_stopwatch.spr"

;### test2

;show_phases=1

;phases_x=10

;phases_y=10

;phases_bmp="tacho02.spr"

;### test3

;show_phases=1

;phases_x=100

;phases_y=100

;phases_bmp="fixing_car.spr"

;### test4

;show_phases=1

;phases_x=0

;phases_y=0

;phases_bmp="earth_rot_60x60.spr"

#####

[local]

dateformat=6 ;(dd-mm-yyyy)

timeformat=0 ;(24h)

default_language="english GB"

;voice_key="tts_nua_dut_f1"

voice_key="tts_loq_dut_f4"

#####

[map]

car2wp_as_route=1 ;(1)

;speedwarn_icon=".spr" ;default

;speedwarn_icon=".spr" ;changed MySpeedCams.spr -> DefPhase=navigation.curr_speedcam.category

sieve_mode=0 ;(1) ??

;rasterorder="" ;google?

enable_new_road_visibility=1 ;(1)

alternative_roadnames=1

2dheadup=1 ;(0) extra 2d heading/north

map_mode=3D

zoomfactor=105 ;(<100 or >100)

tiltfactor=30 ;(150) below 100 smaller tilt steps

;tiltmaxcount=120 ;(100)

;minimum_zoom_amount=70 ;(2)

zoom_handler_click_time=200 ;(100)

3d_zoomfactor=105 ;(<100 >100) below 100 smaller zoom steps

show_labels=1 ;(1)

show_labels_in_2d=1 ;

show_labels_in_3d=1 ;

poi_grouping_distance=0 ;(??)

;poi_distant_zoomlevel=5000 ;(3000)

poi_iconid_distant=1 ;(0) see ui_igo8iconspoi.poi.icons 1st line

poi_iconid_near=1 ;(1) see ui_igo8iconspoi.poi.icons 2nd line

;housenr_corner_offset=2 ;(xFF00)

;

;jun08 version

;tmczoommin=1

;tmczoommax=40

;tmczoommini=1 ;(1)?

;tmczoomsmall=5 ;(8000)

;3d_tmc_road_extra_width=1 ;(0)

roadblockicon_maxzoom=2000 ;(?) tmc icons visible zoom

;

;viewpreset_front1="30,100,7200,10"

;viewpreset_front2="140,7000,6000,10"

;viewpreset_top="600,50000,225,10"

;viewpreset_front3="140,7000,6000,10"

inertia_on_map_move=0 ;(0) panning the map stops slow

autoscroll_on_click gives problem with smartzoom/viewcontrols

autoscroll_on_click=0 ;(0) 1 touch screen acts as joystick moving the map

stop_rotate_on_map_move=1 ;(?)

nightmode_dependent_backlight=1 ;(1)

follow_gps=1 ;(1)

popup_info=0 ;(1) register a script first

zoomscale_disappearing=1 ;(0) works with show_zoombar

auto_nightmode=1 ;(1) see also nightmode

show_oneway=1 ;(1)

textured_poly=0 ;(1) doesn't matter, igo always set it to 1

;terrain_in_2d=1 ;(1)

raster_in_2d=0 ;() like google maps raster

raster_2d_high_quality=0 ;()

shapes_in_2d=1 ;()

3d_brunnel_shutdown=5 ;(24) ?

3d_landmarks=1 ;(1) .3dl files

3d_buildings=0 ;(1) .3dc files

3d_buildings_distance=3 ;(1) far

;3d_dem=1 ;(1) terrain details

3d_dem_detail=3 ;(3)

3d_roads=1 ;(1)

3d_tunnels=1 ;(1)

;### only if smartzoom is not on

3d_min_zoomlevel=20 ;(30) see also [smartzoom] min/maxzoom

3d_max_zoomlevel=500 ;(600)

3d_max_tiltlevel=8200 ;(7800) see sky or not?

3d_default_tiltlevel=7800 ;(6000) between min and max [interface]defaulttilt3d

3d_max_zfar=128 ;(64) 32 Perspective?

3d_scale_carmodel=1 ;(1)

3dcarsizemin=6000 ;(10000)

3dcarsizemax=12000 ;(28000)

3dcarsizemul=40000 ;(40000)

;minPolyDistances0 = 500 ;(300)

;minPolyDistances1 = 500 ;(300)

;minPolyDistances2 = 500 ;(300)

;minPolyDistances3 = 500 ;(300)

;maxPolyDistances0 = 2000

;maxPolyDistances1 = 3000

;maxPolyDistances2 = 4000

;maxPolyDistances3 = 5000

;minTrackDistances0 = 500

;minTrackDistances1 = 500

;minTrackDistances2 = 500

;minTrackDistances3 = 500

;maxTrackDistances0 = 2500

;maxTrackDistances1 = 3500

;maxTrackDistances2 = 4500

;maxTrackDistances3 = 5500

maxFovRatioForPoly=10 ;(5)

track_field_size0=10 ;(10)

track_field_size1=30 ;(30)

track_field_size2=100 ;(100)

track_field_size3=200 ;(200)

track_field_size4=400 ;(400)

solid_field_size0=80 ;(80)

solid_field_size1=100 ;(100)

solid_field_size2=200 ;(200)

solid_field_size3=400 ;(400)

solid_field_size0=800 ;(800)

;max_road_segment_count=1000 ;(2000) faster!

max_road_segment_count=500 ;(2000) faster!

building_render_distance_far_front=6.0

building_render_distance_far_back=3.0

building_render_distance_medium_front=3.0

building_render_distance_medium_back=2.0

building_render_distance_near_front=2.0

building_render_distance_near_back=2.0

#####

[msnd]

; How does msdn work? Movies, Weather, Petrol prices, etc.....

; Set msnd.start=0 to disable

msnd.start=0

msnd.version=1

fw_upgrade.enabled=0

fw_upgrade.image_path="Storage Cardmsnd.firmware.z"

comm.port=99

comm.thread_priority="normal"

comm.dt_read_write_tmout=0.1

comm.send_frame_retry_limit=3

comm.dt_send_tmout=1.0

```
comm.dt_alive_tmout=5.0
ui.selected_fuel_type="regular"
ui.fuel_price_limit_low=3.15
ui.fuel_price_limit_high=3.20
cache.tmc.thread_priority="low"
cache.tmc.dt_delete_expired_tmout=3600.0
cache.tmc.dt_max_sleep=3600.0
cache.gas.thread_priority="low"
cache.gas.dt_refresh=3600.0
cache.gas.dt_download_tmout=30.0
cache.gas.allow_unknown=true
cache.movies.thread_priority="low"
cache.movies.dt_refresh=3600.0
cache.movies.dt_download_tmout=30.0
cache.group_message.thread_priority="low"
cache.group_message.dt_expire_check=300.0
cache.weather.local.thread_priority="low"
cache.weather.local.dt_expire_check=300.0
cache.weather.non_local.thread_priority="low"
cache.weather.non_local.dt_expire_check=300.0
cache.weather.alerts.thread_priority="low"
cache.weather.alerts.dt_expire_check=300.0
provider.tmc.dt_check=0.5
```

```
#####
```

```
[modules]
```

```
### BETTER put them in your CONFIGDEVICES INI file!
```

```
###PIO
```

```
;IEXTERNAL_BACKGROUND_PLAYBACK_MANAGER="PIONEER_EX  
TERNAL_BACKGROUND_PLAYBACK_MANAGER"
```

```
;IOSVOLUME_MANAGER="PIONEER_OSVOLUME_MANAGER"
```

```
;IBACKLIGHT_DRIVER="NULL_BACKLIGHT_DRIVER"
```

;ISKIN="PIONEER_SKIN"

;ITTS="TTS_NUANCE"

;###BECKER

;IOSVOLUME_MANAGER="BECKER_OSVOLUME_MANAGER"

;IPHONE_MANAGER="BECKER_PHONE_MANAGER"

;IOASIS_BLUETOOTH_MANAGER="BECKER_BLUETOOTH_MANAGER"

;ISKIN="BECKER_SKIN"

;### IGO 8.3.x

;IANNOUNCER="ANNOUNCER"

;IAPPLICATION="IGOAPPLICATION"

;IBACKLIGHT_DRIVER="NULL_BACKLIGHT_DRIVER"

;IBACKLIGHT_DRIVER="WINCE_BACKLIGHT_DRIVER"

;IBACKUP_MANAGER="BACKUP_MANAGER"

;IBATTERY="NULL_BATTERY"

;IBATTERY="BATTERY_UNIDEF"

;IBATTERY="BATTERY_MINGSHANG"

;IBATTERY="BATTERY_CARRADIO"

IBATTERY="BATTERY_MONITOR_WINCE"

;IRCT_TILEPROVIDER="GOOGLEMAPS_TILEPROVIDER"

;IRCT_TILEPROVIDER="RCT_TILEPROVIDER_IMPL"

;IBLOCKEDROADS_LIST="BLOCKEDROADS_LIST"

;IBLOWFISHFACTORY="MIO"

;IBLOWFISHFACTORY=BLOWFISHFACTORY_IMP"

;ICACHE="CACHE_IMP"

;ICAR_PROVIDER=""CAR_PROVIDER"

;ICLEARCHANNEL_TMC="CLEARCHANNEL_TMC"

;ICL_SERVER="CL_SERVER"

;ICON_MANAGER_HEKK="ICON_MANAGER_HEKK"

;IDATETIME_FORMATS="DATETIME_FORMATS_IMP"

;IDEVLOCK_KEYGENERATOR="STD_DEVLOCK_GENERATOR"

```
;IDIME="DIME_PINYIN_GENERAL_IMP"

;IDIRECTION_NOTIFY="DIRECTION_NOTIFY"

;IDRIVERALERT_HANDLER="DRIVERALERT_HANDLER"

;IEVENT_SERVER="EVENT_SERVER"

;IEXTERNAL_BACKGROUND_PLAYBACK_MANAGER="STD_EXT_BG_PLAYBACK_MGR"
;IEXTERNAL_BACKGROUND_PLAYBACK_MANAGER="SKYPINCAR_EXT_BGPLAYBACK_MGR"
;IEXTERNAL_BACKGROUND_PLAYBACK_MANAGER="KRS_EXT_BG_PB_MGR"
;IEXTERNAL_BACKGROUND_PLAYBACK_MANAGER="ISUZU_EXT_PLAYBACK_MANAGER"
;IEXTERNAL_BACKGROUND_PLAYBACK_MANAGER="INTERROAD_EXT_PLAYBACK_MANAGER"
;IEXTERNAL_BACKGROUND_PLAYBACK_MANAGER="IGO_2006_LEGACY_EXT_BG_PB_MGR"
;IEXTERNAL_BACKGROUND_PLAYBACK_MANAGER="HAWK_EXT_BGPLAYBACK_MGR"
;IEXTERNAL_BACKGROUND_PLAYBACK_MANAGER="GPV1007_EXT_BGPLAYBACK_MGR"
;IEXTERNAL_BACKGROUND_PLAYBACK_MANAGER="GPV1004_EXT_BGPLAYBACK_MGR"
;IEXTERNAL_BACKGROUND_PLAYBACK_MANAGER="GPSANDMORE_EXT_BGPLAYBACK_MGR"
;IEXTERNAL_BACKGROUND_PLAYBACK_MANAGER="GEN_REG_EXT_BGPLAYBACK_MGR"
;IEXTERNAL_BACKGROUND_PLAYBACK_MANAGER="FUJITSUTEN_EXT_BGPLAYBACK_MGR"
;IEXTERNAL_BACKGROUND_PLAYBACK_MANAGER="BESTCREATIVE_EXT_BGPLAYBACK_MGR"
;IEXTERNAL_BACKGROUND_PLAYBACK_MANAGER="ANSON_EXT_BGPLAYBACK_MGR"
;IEXTERNAL_BACKGROUND_PLAYBACK_MANAGER="ALPINE_EXT_BGPLAYBACK_MGR"
;IEXTERNAL_BACKGROUND_PLAYBACK_MANAGER="ACR_EXT_BG_PLAYBACK_MGR"

;IEXTERNAL_REGIONAL_CONFIG="STD_EXTERNAL_REGIONAL_CONFIG"
;IEXTERNAL_REGIONAL_CONFIG="UNIHAM_EXTERNAL_REGIONAL_CONFIG"
;IEXTERNAL_REGIONAL_CONFIG="HAWK_EXTERNAL_REGIONAL_CONFIG"
;IEXTERNAL_REGIONAL_CONFIG="LCP_EXTERNAL_REGIONAL_CONFIG"

;IEXT_DIRECTION_NOTIFIER="NULL_DIRECTION_NOTIFIER"
;IEXT_DIRECTION_NOTIFIER="ZENEC_DIRECTION_NOTIFIER"
;IEXT_DIRECTION_NOTIFIER="ALPINE_DIRECTION_NOTIFIER"

;IFAVORITE_MANAGER="FAVORITE_MANAGER"

;IFFSPRITE_CACHE="FFSPRITE_CACHE"

;IFILEREAD_MANAGER="FILEREAD_MANAGER"
```

```
;FILESYS="FILESYS"

;FLEETMANAGEMENT="FLEETMANAGEMENT"

;FLEETMGMT_CORE="FLEETMGMT_CORE"

;IFM_TRANSMITTER="NULL_FM_TRANSMITTER"

;IFM_TRANSMITTER="ALPINE_FM_TRANSMITTER"

;IFM_TRANSMITTER_MANAGER="FM_TRANSMITTER_MANAGER_I MP"

;IGEOCODER="?????" ;Something with outlookpoi

;IGEODB_SEARCH="GEODB_SEARCH"

;IAPPLICATION="IGOAPPLICATION"

;IGPSTMC_EVENT_QUEUE="GPSTMC_EVENT_QUEUE"

;IGPSTMC_LOGGER="RDS_BINARY_PACKET_DUMPER"

;IGPSTMC_LOGGER="RDS_TEXT_PACKET_DUMPER"

;IGPSTMC_LOGGER="RDS_GNS_LOGGER"

;IGPSTMC_SOURCE="RDS_GPS_PLAYER_SOURCE"

;IGPSTMC_SOURCE="HDLIB_HDTMC_SOURCE"

;IGPSTMC_SOURCE="RDS_GPSTMC_ALPINE"

;IGPSTMC_SOURCE="KRI_HDTMC_SOURCE"

;IGPSTMC_SOURCE="RAW_RDSLOG_GPSTMC_SOURCE"

;IGPSTMC_SOURCE="RDS_GPSTMC_BLAUPUNKT"

;IGPSTMC_SOURCE="WONDEPROUD_GPSTMC_SOURCE"

;IGPSTMC_SOURCE="UNIDEN_GPSTMC_SOURCE"

;IGPSTMC_SOURCE="HDTMCLOG_GPSTMC_SOURCE"

;IGPSTMC_SOURCE="AVQ_GPSTMC_SOURCE"

;IGPSTMC_SOURCE="NMEA_GPSTMC_GNSPORT"

;IGPSTMC_SOURCE="NMEA_GPSTMC_GLOBALSAT"

;IGPSTMC_SOURCE="RDS_GPSTMC_SILICONLAB"

;IGPSTMC_SOURCE="NMEA_GPSTMC_HYUNDAI"

;IGPSTMC_SOURCE="GNSLOG_GPSTMC_SOURCE"

;IGPSTMC_SOURCE="HARMAN_GPSTMC_SOURCE"

;IGPSTMC_SOURCE="NMEA_GPSTMC_FX"

;IGPSTMC_SOURCE="NGALIK_GPSTMC_SOURCE"

;IGPSTMC_SOURCE="NMEA_GPSTMC_AMARYLLO"
```

```
;IGPSTMC_SOURCE="NMEA_GPSTMC_ROYALTEK"  
  
;IGPSTMC_SOURCE="NMEA_GPSTMC_SAMSUNG"  
  
;IGPSTMC_SOURCE="NMEA_GPSTMC_V2"  
  
;IGPSTMC_SOURCE="NMEA_GPSTMC_V1"  
  
;IGPSTMC_SOURCE="ETEN_GPSTMC_SOURCE"  
  
;IGPSTMC_SOURCE="GNS_GPSTMC_SOURCE"  
  
  
;IGPS_DRIVER="GPS_DRIVER"  
  
;IGPS_DRIVER="EMPTY_GPS_DRIVER"  
  
;IGUI="GUI_IMP"  
  
;IHISTORY_MANAGER="HISTORY_MANAGER"  
  
;IICON_MANAGER="ICON_MANAGER"  
  
;ILICENSE_MANAGER="LICENSE_MANAGER"  
  
;IMD5="MD5_IMP"  
  
;ILICENSE_MANAGER="NULL"  
  
  
IOSVOLUME_MANAGER="STD_OSVOLUME_MANAGER"  
  
;IOSVOLUME_MANAGER="STD_EMPTY_OSVOLUME_MANAGER"  
  
;IOSVOLUME_MANAGER="MAPTRAX_OSVOLUME_MANAGER"  
  
  
;IPHONE_MANAGER="PHONE_MANAGER"  
  
  
;#### PHONE_PROVIDER_%S -> [phone] driver="%s"  
  
;IPHONE_PROVIDER="PHONE_PROVIDER_SOL"  
  
;IPHONE_PROVIDER="PHONE_PROVIDER_SAMSUNG"  
  
;IPHONE_PROVIDER="PHONE_PROVIDER_ROUTON"  
  
;IPHONE_PROVIDER="PHONE_PROVIDER_PHONELINK"  
  
;IPHONE_PROVIDER="PHONE_PROVIDER_TAPI"  
  
;IPHONE_PROVIDER="PHONE_PROVIDER_NGALIK"  
  
;IPHONE_PROVIDER="PHONE_PROVIDER_NFORE"  
  
;IPHONE_PROVIDER="PHONE_PROVIDER_IVT"  
  
;IPHONE_PROVIDER="PHONE_PROVIDER_IGOMGS"  
  
;IPHONE_PROVIDER="PHONE_PROVIDER_HF"  
  
;IPHONE_PROVIDER="PHONE_PROVIDER_GSAT"
```

```
;IPHONE_PROVIDER="PHONE_PROVIDER_FAKE"

;IPHONE_PROVIDER="PHONE_PROVIDER_BT"

;IPHONE_PROVIDER="PHONE_PROVIDER_BRASALFA"

;IPHONE_PROVIDER="PHONE_PROVIDER_BCE"

;IPHONE_PROVIDER="PHONE_PROVIDER_AVT"

;IPHONE_PROVIDER="PHONE_PROVIDER_ASUSHF"

;IPHONE_PROVIDER="PHONE_PROVIDER_BASE"

;IPOWERMGMT_PROVIDER="STD_POWERMGMT_PROVIDER"

;### might help suspend/resume problems. use in CONFIGDEVICES INI

;IPOWER_DRIVER="PDA_POWER_DRIVER"

;IPOWER_DRIVER="WINCE_POWER_DRIVER"

;IPOWER_DRIVER="PASSIVE_POWER_DRIVER"

;IPOWER_DRIVER="NULL_POWER_DRIVER"

;IPOWER_DRIVER="UNIHAM_POWER_DRIVER"

;IPOWER_DRIVER="UNIDEN_POWER_DRIVER"

;IPOWER_DRIVER="MAPTRAX_POWER_DRIVER"

;IPOWER_DRIVER="HAWK_POWER_DRIVER"

;IPOWER_DRIVER="ALPINE_POWER_DRIVER"

;IPOWER_MANAGER="POWER_MANAGER"

;IROOTDIR_FACTORY="ROOTDIR_FACTORY"

;ISAVEDROUTEMANAGER="SAVEDROUTEMANAGER"

ISKIN="IGO8_SKIN"

;ISKIN="UNIHAN_VIRGO_SKIN"

;ISKIN="INTERROAD_SKIN"

;ISKIN="BESTCREATIVE_SKIN"

;ISKIN="ALPINE_SKIN"

;ISKIN="AIRIS_SKIN"

;ISOUND_SYSTEM="SOUNDSYSTEM_HEKKUS"

ISURFACE="SURFACE_GX"
```

```
;ISURFACE="SURFACE_GXOVERGDI"
```

```
;ISURFACE="SURFACE_GDI"
```

```
;ISYSCONFIG="SYSCONFIG"
```

```
;ITHEME_MANAGER="THEME_MANAGER"
```

```
;ITMC_CONFIGURATION="TMC_CONFIGURATION"
```

```
;ITMC_CONNECTOR="TMC_CONNECTOR"
```

```
;ITRUCK="TRUCK"
```

```
;ITTS="TTS_LOQUENDO"
```

```
;ITTS_TEST="TTS_TEST"
```

```
;IUSERLISTMODEL="USERLISTMODEL"
```

```
;IWINMAIN="WINDOWS_MESSAGE_HANDLER"
```

```
;IWINSYSHOOK="ASUS_KEYBOARD_HOOK"
```

```
;IWINSYSHOOK="NULL_KEYBOARD_HOOK"
```

```
;IWINSYSHOOK="WINCE_KEYBOARD_HOOK"
```

```
;IOASIS_BLUETOOTH_MANAGER="OASIS_BLUETOOTH_MANAGER "
```

```
#####
```

```
[mydata]
```

```
use_home=1 ;(0) defaultsuser.upoi
```

```
use_work=1 ;(0) defaultsuser.upoi
```

```
max_favorites=99 ;(30)
```

```
empty_favorites=1 ;(1) allow favorites to be empty
```

```
max_histories=99 ;(?)
```

```
num_favicons=7 ;(0) UI_IGO8ICONSFAVICON1 2 3 4 5 6 7.ICON
```

```
#####
```

```
[mydata.tracks]
```

```
auto_track_visible=1 ;(0)
```

```
record_auto_track=0 ;(0)
```

```
:[mydata.truck]
```



```
;default_profile="default"

;selected_profile=0 ;(-1) from truck_profiles.ini

;drive_alone=1 ;(1)

;selected_driver=0

;driving_timer_allowed=1 ;(1)

;max_driving_time= ;(0xF70000)

;max_daily_driving_time= ;(0x1EE6280)

;min_break_time=

;max_break_time=

;pre_warn_time=

;start_stop_limit=15 ;(15)

;### truck_prolifes.ini

;## vtr

;## hazard

;## icon

;## trailers

;## axles

;## actualweight

;## maxspeed

;## weight

;## height

;## width

;## length

;## name

;#####
```

[navigation]

```
direction_notify=1 ;(0) like start_ne start_se start_n in voice.zip commands.csv?

;onlyguidancetime=5 ;(0) skip to secs before next manoeuvre

;onlyguidancedist=500 ;(100) when simulate skip to distance before next manoeuvre

no_road_rotate_speed_min=20 ;(10)

waypoint_radius=800 ;(300) waypoint visited if < 300 mtr?

waypoint_radius_multiplier=1 ;(1)
```

```
show_city_in_next_street=1 ;(1)
sim_speed_factor=4 ;(1?)
show_current_city=1 ;(1)
show_countrychange=1 ;(0)
autoreplan_action="AUTO" ;(ASK AUTO OFF)
gps_pos_to_road=1 ;(1)
skip_grab_viewchanging=0 ;(0)
maneuver_near_threshold=1000 ;(1500)
second_maneuver_near_threshold=1500 ;(1800)
;maneuver_distance_diff_threshold=100 ;(300)
can_pass_via_from_itinerconfig=1 ;(0)
```

```
#####
```

```
[oasis]
```

```
;include_directories="My Flash Disk"
;game_root="My Flash DiskGames"
;contacts_single_poi=1
```

```
#####
```

```
[other]
```

```
demo_mode=3 ;(0) enables demo route mode
;alpine=1 ;(0) enables alpine fm transmitter?
```

```
[other.fm_transmitter]
```

```
fmtx_enabled=0
;min_freq=
;max_freq=
;store_slot_max=
;fm_tx_current_frequency=
```

```
[other.highway_drive]
```

```
enabled=1
use_signposts=1
```

```
calculate_simulation=1

poi_search=1 ;()

;poi_search_area=1500 ;()

;planned_route_only=1 ;()

;precog_distance=

;filter_by_pois=

;poi_category_list=""

;signpost_description_max_items=

poi_search_category0="Gas_Station"
poi_search_category1="Parking"
poi_search_category2="Restaurant"
poi_search_category3="Hotel"

[other.magellan]

demo_mode_restart_timeout = 10800

offroute_max_cnt = 3

offroute_timeframe = 60

#####

[patch]

;patch_hwkey_counter=0 ;(0)

#####

[phone]

;### do set in configdevices ini

;driver="TAPI"

;class_name=

;exe_path="Windowsprog.exe"

;win_name="Phone"

;switch_name="-phoneui" ; specify the command line parameters if needed

;start_bt_at_startup=0 ;??

;use_post_message=0 ;(0)

;default_bt_state=0 ;(1)
```

;default_phone_state=0 ;(0)

;phone_msg_type=0 ;(0)

#####

from ezrider r3

[pioneer]

parking_break_speed=160.0

hide_logos=1

#####

[poi]

use_multi_poi_icon=0 ;(1)

;poi_labels=1 ;(1)

;show_poi_boundingrects=1 ;(0)

show_poi_areas=1 ;(0)

use_lastknowngps=1 ;(0)

inherit_visibility=0

default_visibility_altitude=3000 ;(?)

; Airport, Business, Car_Dealer_Repair, Communication, Community, Finance Leisure

; Medical, Nature, Parking, Petrol_Station, Rent_A_Car, Restaurant, Shopping, Sport

; Tourist_Attractions, Transportation

sort_order="Petrol_Station,Parking,My Poi,Restaurant,Shopping,Accomodation,Medical"

("Restaurant,Accomodation,Petrol_Station,Parking, Medical")

priority="Petrol_Station,Parking,My
Poi,Restaurant,Shopping,Accomodation,Medical"

("Restaurant,Accomodation,Petrol_Station,Parking, Medical")

sort_by_config=1 ;(0)

;multipoi=2 ; 0 1 or 2 ????

;no_brands="," ;(,,)

;

userpoi_hasmypoi=1 ;(0) see mydata use_home use_work

enable_pois_before_080217=0 ;might cause crash!

;max_quicksearch="100" ;??

;deviation_divident=4 ;(4)

;detour_interval_1=5000 ;(300)

;detour_interval_2=10000 ;(1000)

;detour_interval_3=30000 ;(5000)

kmlpoi=1 ;(0) in contentuserdatapoi

;kml_icon_priority=100000

kml_draw_as_multipoi=0

kml_show_folder_icon=1

kml_show_please_wait=1

#####

Most powersettings done in configdevicesdefault.ini or other INI file

[power]

battery_full_hyst=4 ;(2)

battery_low_hyst=4 ;(2)

battery_critical_hyst=4 ;(2)

;battery_low_limits="20,15,10,5" ;(20,15)

;battery_critical_limits=0 ;(10,5,3)

;battery_shutdown_at=0 ;(-1 or xFFFFFFFF)

;battery_shutdown_delay=30 ;(10)

see data.zipconfigdevices

skip_resume_process=0 ;(0) might help resume from standby

skip_suspend_process=0 ;(0)

skip_resume_process_all=0 ;(0)

skip_suspend_process_all=0 ;(0)

suspend_state_define="Suspend,BacklightOff,ScreenOff" ;(Suspend,BacklightOff,ScreenOff,Unattended)

```
resume_state_define="On" ;(On)
```

```
sdcard_remove_onsuspend_ignore=1 ;(0)
```

```
;sdcard_remove_delay=5000 ;(5000)
```

```
disconnect_gps_on_suspend=1 ;(1)
```

```
;backlight_sensor=0
```

```
;power_off_mode=0 ;(0)
```

```
;power_off_timeout=300
```

```
;override_battery_values=???
```

```
;battery_warning_limit=10
```

```
#####backlight power settings
```

```
;backlight_sync_with_OS=1
```

```
;backlight_slow_api=1
```

```
powermgm_state=1 ;(0) smart
```

```
;backlight_day=100
```

```
;backlight_night=1
```

```
keep_backlight_on_restore=1 ;(1)
```

```
;allow_battery_full=1 ;(0)
```

```
#####
```

```
[project]
```

```
;name=xxxxx ; default data.zipproject_configigo8_generic.INI
```

```
name=igo8_generic.INI
```

```
;name=igo_easy.ini
```

```
;name=pioneer.ini
```

```
;name=magellan43xx.ini
```

```
;name=becker.ini
```

```
#####
```

```
[rawdisplay]
```

```
;hide_hhtaskbar=1
```

```
;dpi=120

;orientation_restore=1

;orientation_fix_1=1

;jun08 version

;gx_disable_detect=1 ; ok

;gx_force_using_dll=1 ; or gx.dll?

;gx_allow_gaps=1 ; huh?

;

;highres=0

;driver=GX ;GDI GX GLESS

class="auto"

; or rlandscape, portrait, square,wide, auto

;screen_x=320

;screen_y=240

;screen_x=480

;screen_y=272

;offset_x=-20

;offset_y=40

;stretch=1

;#####

[roundaboutcam]

enabled=0 ;(1)

centery=70 ;(50) cam tilt @ roundabout

;#####

[route]

;### If you change any of these !!!!! delete .SAVERoute.dat first !!!!!

correctness=95 ;(90) see also [defaults] mainroadness etc...

route_type=ECO ;(FAST,ECO,SIMPLE,SHORT,SCENIC)
```

planned_route_weight=7 ;(7) 0 to 10 Off Route Sensitivity (route.planned_route_weight)

use_tmc=1

calc_alternative_route_enabled=1 ;(1)

sort_cityresult_by_gpsdistance=1 ;(0)

straight_start_on_recalc=0 ;(0) del prev route?

allow_save_route=1 ;(1)

uturn_penalty=5000 ;(1000)

zip_resolve_address=1 ;(1)

zip_resolve_max_length=10 ;(0)

city_show_coszip=1 ;(0)

city_show_streetzip=1 ;(0)

streetzip_max_length=10 ;(0)

;max_segs_between_wp_entries=10 ;(10)

;strap_waypoint_to_entry=0 ;(0)

;handle_freeway_as_highway=1 ;(1)

allow_unpaved=0

allow_highway=1

allow_ferry=1

allow_charge=1

allow_uturn=0

allow_special=0

allow_carpool=0

cross_border_routes=1 ;(1)

;scenic_highway_weight=200 ;(200)

;scenic_scenic_weight=50 ;(50)

;vehicle_type=0 ;(0) Car

slow_car_speed=60 ;(80) eta, route time calc?

slow_car_multiplactor=80 ;(80)

fast_car_speed=100 ;(130)

fast_car_multiplactor=100 ;(100)

motorcycle_speed=120 ;(130)

motorcycle_multiplactor=100 ;(100)

offroad_speed=20 ;(30)

continue_with_ferry=1 ;(0)

max_endpoint_distance_km_pedestrian=100 ;(0)

max_endpoint_distance_km_bicycle=200 ;(0)

max_endpoint_distance_km_shortest=1500 ;(0)

max_endpoint_distance_km_limited=1500 ;(0)

max_endpoint_distance_km=2000 ;(0)

stop_on_highway=1 ;(1)

permit_penalty=1000 ;see [truck]

charge_penalty=1000 ;(0)

toll_penalty=0 ;(0)

bridge_penalty=100 ;(0) in meters?

tunnel_penalty=200 ;(0)

#####

[route.histspeed]

enabled=1 ;(1)

show=0 ;(0)

use_timeslice=1 ;(0)

[route.histspeed.timeslice]

day=0 ;(0)

hour=0 ;(8)

minute=30 ;(0)

#####

[settings]

;default values, those are not read by igo?, see savesystem.ini

accident_recalc=0

closed_recalc=0

closures_recalc=0

congestion_recalc=0

danger_recalc=0

heavy_recalc=0

invalid_recalc=0

police_recalc=0

roadworks_recalc=0

weather_recalc=0

accident_panel=1

closed_panel=1

closures_panel=1

congestion_panel=1

danger_panel=1

heavy_panel=1

invalid_panel=1

police_panel=1

roadworks_panel=1

weather_panel=1

accident_map=1

closed_map=1

congestion_map=1

closures_map=1

danger_map=1

heavy_map=1

invalid_map=1

police_map=1

roadworks_map=1

weather_map=1

all_map=1 ;(1) show all on map (all event types)

#####

[scheduler]

disable_smooth_anim=1 ;(0)
;logic_tick_length=20 ;(20)
;logic_burst_length_low_performance=200 ;(200)
;logic_burst_length
;logic_max_backlog
;idle_high_priority_time_slice=300 ;()
;idle_maximum_time_slice= ;()
;idle_ideal_time_slice= ;()
stuck_key_timeout=2000 ;(60000)

#####

[screen]

;nightmode=0 ;(0)
menu_animation=0 ;(0)
;focus_followlinks=1
;focus_list_move_before_scroll=1
;focus=1
;focus_type= ; Off Icon Bmp
;focus_color
;focus_sprite=""
;focus_halign=center
;focus_valign
;focus_list_keyup
;focus_list_keydown
;focus_list_keyleft
;focus_list_keyright
;focus_activator_key

keyboard_character_repeat=1
keyboard_repeat_delay=500
keyboard_repeat_rate=250

#####

[smartzoom]

smartzoom tilt starts in 850 mtrs before next manœuvre

use2d is to use separate smartzoom for 2d and 3d.

Once this is implemented in a UI it should be set to 1.

use2d=1 ;(1)

auto_follow_on=1 ;(1)

auto_follow_time=10 ;(10) sec

restore_smartzoom_on=1 ;(0)

auto_smartzoom_time=10 ;(10) sec

zoom_after_find=1 ;(1)

autozoom_address=300 ;(700)

autozoom_coord=1000 ;(8000)

autozoom_cos=1000 ;(8000)

2D smartzoom

enabled2d=1 ;(1)

minzoom2D=100 ;(200) zoom in level 2d

maxzoom2D=1500 ;(1000) zoom out level

zoom2dpercent=135 ;(135)

3D smartzoom

enabled=1 ;(1)

minzoom=60 ;(60) not <60 not smaller than 3d_min_zoomlevel

maxzoom=100 ;(300) not bigger than 3d_max_zoomlevel

minangle=45 ;(45) like 3d_default_tiltlevel (8000)

maxangle=80 ;(70)

angleoffset=10 ;(10)

percentage=50 ;(100) also search ui's for .smartzoom.percentage

;### overview

overview=1 ;(0)

overview_zoomlevel=2500 ;(2816)?

overview_distance=10000 ;(4000)?

#####

[sound]

;amplification=1.0 ;(1.0) ????

;sound_on_click=0 ;(0)

;resume_delay_time=0 ;(0)

;ding_min_delay=0 ;(0)

announce_viadest_side=1 ;(1)

;announce_street_name=1 ;(1)

;native_osvolume_linear=1 ;(0)

;use_os_volume=1 ;(0)

;os_volume=255 ;(127)

os_amplifacation=1.0 ;(1.0)

;auto_mute=1 ;(0)

queue_length=200

ding=0 ;(1)

sound_volume=255

voice_volume=255

sound_muted=0

voice_muted=0

;device_samplerate=

;device_bps=

;device_stereo=

;suspend_time=1000 ;(3000) 3 sec timeout for wavedev to goto sleep?

dynamic_volume_type=1 ;(1)

dynamic_volume_minspeed=60 ;(90)

dynamic_volume_maxspeed=130 ;(150)

dynamic_volume_voicemaxspeed=80 ;(120)

dynamic_volume_voice_volume_max=75 ;(64)

dynamic_volume_os_volume_max=255 ;(255)

incomingcallsetting=1

;device_id=0

;method5_maxvolume=xFFFF ;(0xFFFF)

;used_byte_in_method=1 ;(1)

;use_method=5 ;(0)

#####

[sound.announcer]

recalculate=1

ask_recalculate=1

offroute=1

;traffic_jam=1 ;test

;eta=1 ;test

overspeed=1 ;(1)

gps_disconnected=1 ;(1)

gps_signal_lost=1 ;(1)

mute_all=0

muted=0 ;(0)

;recalculate_min_delay=15 ;(15)

;recalculate_max_delay=180 ;(180)

#####

:[speedcam]

;import_directory="Storage Cardpoispeedcam" ; from ezrider r

;disable="_USA,_CAN,_u**,_ual,_uak,_uak,_uaz,_uar, _ucx"

#####

[strapon]

discard_state_timeout=10000 ;(30000) 30 secs

max_position_distance=800 ;(300)

min_gps_precision=50 ;(0) gps.accuracy

```
max_gps_precision=100 ;(0) gps.accuracy
;min_discard_prob= ;(????)
min_distance_for_move_at_low_speed=50 ;(20)
max_speed_for_stop=3 ;(0)
min_distance_for_switch_off_stopping=100 ;(100)
min_speed_for_release_stopping_off=20 ;(10)

;#####

[timezone]
default_timezone=29 ; GMT+1 amsterdam
index=29
sync_time=1
reset_os_timezone=0
sync_os_timezone=1
use_auto=1
manual_dst=0
tzdst=0
;patch_dst=0 ;(0)
;auto_index=290
;use_timezone_setting_fix=1
use_new_timezone_ini=1
;timezone_key="Time Zones"
keep_auto_on_error=1 ;()

;#####

[tmc]
;###GETSYSENTRY
show_tmc_settings=1
use_tmc_subscription=1
;init_on_startup=1 ; set in CONFIGDEVICES INI
reinit_on_hardware_lost=0
;###
```

```
;hardware_search_off=1 ;(0)

min_rds_health_check_time=2000 ;(4000)

min_rds_health=6 ;(4)

step_over_search_on=0 ;(1)

scansearch_threshold=8 ;(7)

onstation_threshold=4 ;(3)

;tuner_alg_search_timeout=4000 ;(4864)

;tuner_alg_search_force_on=1 ;(1)

tuneralg_rds_packet_timeout=1000 ;(1000)

;tuneralg_8a_packet_timeout=2304 ;(2304)

;tuneralg_3a_packet_timeout=5376 ;(5376)

tuneralg_last_8a_packet_timeout=5000 ;(?)

;ignore_all_events=0 ;(0)

no_events_max_timer=600 ;(300) secs?

;tmc_announce_timer=90

new_event_recalc_timeout=5 ;(1)

changed_event_recalc_timeout=20 ;(1)

;

enable_subscription=1 ;(0) subscribe button in tmc config

;show_affected_with_onroute_events=0 ;(0) what this does

enable_igo_provider=1 ;(0)

auto_tuning=1 ;(0)

auto_calc_detour_event=0 ;(0) type of events?

calc_detour_route=0 ;(0)

auto_detour_calc=0

announce_total_route=0 ;(0) only announce what is in front?

enable_flow_icons=1 ;(0) need .spr

events_custom_color=1 ;(0) see day2dcolor.ini/day3dcolor.ini tmc_event_color0 ...

enable_flow_events=1 ;(0) haven't seen any flowing

flow_stripe_width=6 ;(6)
```



```
flow_stripe_offset=0 ;(0)
flow_stripe_blinking_time=1000 ;(0) in msec
;cache_root="content"
;cache_name="tmc/tmccache" ;(?)
flow_limit_low=15
flow_limit_high=45

;### extra settings ezrider r3
enable_flow_lines=1
disable_fast_flow_lines=1
hide_fast_speed_values=1
flow_line_width_from_viscfg=1
flow_line_offset_from_viscfg=1
flow_line_blinking_time=1500
disable_fast_flow_icons=0
flow_icon_zoom_big=500
flow_icon_zoom_med=3000
flow_icon_sprite_big=".spr"
flow_icon_sprite_medium=".spr"
flow_icon_sprite_small=".spr"
flow_icon_fontname = "tahomabd"
flow_icon_fontsize_big = 16
flow_icon_fontsize_medium = 0
flow_icon_fontsize_small = 0
flow_icon_offset_from_viscfg=1
;###

;### setings for configdevices ini
;port="COM,1"
;baud=38400
;source=gns
;harman eten galik opentmc2 opentmc1 hyundai samsung amaryllo royaltek gns

;internal_tmc_name="amaryllo"
```

```
;detect_config_amaryllo=",,WISTRON"
```

```
;port_cfg
```

```
= "COM,1,38400,8,ONESTOPBIT,true,NOPARITY,DTR_CONTR  
OL_ENABLE,RTS_CONTROL_ENABLE,true,true,false,false  
,true,false,false,false,0,fa
```

```
lse,0,0,0,0,false,0"
```

```
;wait_rxchar_onread=1
```

```
#####
```

```
[tracklog]
```

```
track_block_size=1000 ;(500)
```

```
track_max_size=2048 ;(?)
```

```
#####
```

```
[tripcomputer]
```

```
;num_of_trips=3 ;(3)
```

```
#####
```

```
###
```

```
### use=1 overrides all vehicles, better use SAVEtruck_profiles.ini method
```

```
###
```

```
[truck]
```

```
vtr=519 ;default truck VTR
```

```
max_restriction_level=0
```

```
;use=1 ;(?)
```

```
;weight="10000" ;(?)
```

```
;weightperaxle="2000" ;(-1)
```

```
;loadtype="-1" ;(-1)
```

```
;maxspeed="90" ;(?)
```

```
;length="15" ;(?)
```

```
;width="3.5" ;(?)
```

```
;height="4.5" ;(?)
```

;max_restriction_level="2" ;(0)

;vtr="1"

;hazmatflags="5" ;Hazardous Materials 0-6

;### see also [route] permit_penalty=2000

#####

[tts]

automatic_direction_conversion=1 ;(1)

tts_buffer=131072 ;(32786=32k)

announce_exit_directions=1 ;(0)

tts_logics=6 ;(2)

priority="HIGH" ; ezrider r3

always_say_road_names=3 ;(0) 1 or 2 or 3

skip_exit_numbers=2 ;(0) 1 or 2

;tts_log_announce=1 ;(0)

;tts_gc_size=0 ;(0)

;init_on_thread=1 ;(1)

;tts_test=1 ;(0)

;memcounter=1 ;(0)

;tts_gc_size=524288

#####

[warning]

speedcam_enabled=1 ;(0)

speedcam_visualtype=1 ;(1)

speedcam_soundtype=1 ;(1) 1=warn if overspeed 2=approach

speedcam_warning=1 ;(0)

speedlimit_warning=1 ;(1)

speedlimit_warning_voice=1 ;(1)

speedlimit_warning_visual=1 ;(1)

speedwarn_alt_builtup_based=1 ;(0)

speedwarn_alt_limit=1 ;(0)

speedwarn_alt_tolerance=110 ;(100)
speedwarn_alt_toltype=1 ;(0) alternative tolerance type

speedwarn_tolerance=110 ;(100)
speedwarn_toltype=1 ;(0) absolute or percentage

lowspeed_warning=0 ;(1)
lowspeed_toltype=0 ;(0) percentage
lowspeed_tolerance=20 ;(20)

pedestrian_warning=0 ;(1)
pedestrian_warning_threshold=40 ;(40)

speedwarn_voice_rewarn_toltype=1 ;(0)
speedwarn_voice_rewarn_tolerance=110 ;(-1)

approach_beep_distances="8,16,24" ;("8,16,24")
warn_distances="120:600,100:400,80:300,50:100" ;("110:1000,80:800,60:500,40:300") speed:distance

approach_beep_sound="!sectionbeepB" ;(!sectionbeepB) speedcam approach sound
overspeed_sound="!oasis_alarm1" ;(!alert5) speedcam sound

speedcam_max_angle=44 ;(20) degrees?
speedcam_snap_distance=25 ;(25) snap what?
speedcam_max_lookahead=500 ;(1000) check for cams 500 mtr ahead
speedcam_maxdistance_from_road=30 ;(50) ignore speedcams more than 20 meters from the road

section_beep_distance=50 ;(100) only beep 50 mtr before
max_section_time=240 ;(600) max beep time 240 secs
section_beep_sound="!sectionbeepA" ;(!sectionbeepA)
section_start_sound="!sectionstartA" ;(!sectionstartA)
section_end_sound="!sectionend" ;(!sectionend)

;#####

[warning.driveralert.settings]
max_display_count=2

show_timeout=10

show_vehicle_pictograms=1

;truck_policy=

;show_cat=

;warn_cat=

;warn_method=

;#####

sys.txt